Animation Tab

The Animation Tab is shown below.This provides the various adjustments and parameters to control animation of objects.



- For Pan and Rotate, adjustments can be made in three planes
  - X,Y and Z for Pan
  - C,Y and X for Rotate
- These adjustments replace the 3D parameters provided in Version 8.
- A new adjustment called Framing is provided (see Framing)
- The Color Correction parameters have been expanded in Version 9 (Color Correction)
- The “Key Frame Time” box shows the time (in milliseconds) of the selected Key Frame

Parameter Controls

Display Mode for Pan and Zoom

Click on the “%” sign or the “100%” sign:

- “%” = Percentage Mode
- “px” = Pixels Mode
- “pt” = Original Points Mode
- “100%” = Full Height of Project Screen
- “Original Pixels” = The Original Pixel Size of the Image



The Illustration below shows a 640×480 rectangle at Original Size in a 1920×1080 Project

- In Percentage Mode:

- The values for “X” and “Y” Pan are calculated for the Centre of the Object/Rectangle with respect to the Centre of the Slide
- The value of the Zoom Parameter is the percentage of the Full Height of the Project Screen (in this case 1080 pixels)
- 480/1080= 0.44444444444 = 44.44444444%



- In Pixels Mode:

- The values for “X” and “Y” Pan are calculated for the Top Left Corner of the Object/Rectangle with respect to the Top Left Corner of the Slide
- The value of the Zoom Parameter is the Pixel Size of the Object/Rectangle



- In Points Mode



The Centre Control

- The “CENTRE” Control can be used to move the CENTRE or “Point of Rotation” of an Object as shown below:



The Rotate Control

- The “Rotate C” Control will rotate an Object about its Centre Point in the same plane as the screen:



- The “Rotate Y” Control will rotate an Object about its Centre Point in 3 Dimensions Horizontally:



- The “Rotate X” Control will rotate an Object about its Centre Point in 3 Dimensions Vertically:



- The “C”, “Y” and “X” Rotate Controls can be used simultaneously:



Changing Parameters with the Mouse

- Place the Mouse on any Letter (e.g. X,Y or Z in the Pan Controls) and click and drag left or Right

- You can also Right Click on any Letter and access commonly used Preset Values (See Right Click Menus below)
- You can “double click” on any letter to change the value back to its default state

Keyboard Entry

- In any box, highlight the existing value and type in a new value

OR Place the cursor in a box and:

- UP arrow on Keyboard increases the value by one unit
- DOWN arrow decreases the value by one unit
- Pg Up on Keyboard increases the value by ten units
- Pg Dn on Keyboard decreases the value by ten units

The UNITS depend on the chosen Display Mode:

- In % Mode the units will increase/decrease by 1% or 10% of the Parent Frame (or Background)
- In Px Mode the units will increase/decrease by 1 Pixel or 10 Pixels - relative to Project Size
- In Pt Mode the units will increase/decrease by 1 Pixel or 10 Pixels relative to the Original size of the Object

Pan

- The parameters can be read in Percentage, Pixels or Original Points

- X - Horizontal movement of the Object relative to the width of the Object's Parent Frame
- Y - Vertical movement of the Object relative to the height of the Object's Parent Frame
- Z - Zoom - “Closer to” or “further away from” the viewer

Zoom

- The parameters can be read in Percentage, Pixels or Original Points

- X - The horizontal dimension relative to the native size/resolution of the Object's Parent Frame
- Y - The vertical dimension relative to the native size/resolution of the Object's Parent Frame
- With the “Chain Link” deselected the object can be distorted
- With the “Chain Link” restored the distorted image/object can be scaled
- Shift + Click and Drag on the “bounding box” will temporarily “unlink” the X and Y parameters and allow the object to be “distorted”
- Click on 100% to return to default settings (100%)

The UNITS depend on the chosen Display Mode:

- In % Mode 100% = 100% of the Parent (Slide / Frame etc)
- In Px Mode the Pixel Dimensions of the Object are shown
- In Pt Mode 100% = 100% of the Native Pixels of the Object

The Right Click Menus for X, Y and Z


Close
Properties
Animation
Pan (px)
add modifier
Zoom (px)
Rotate
Center
Framing
Opacity
Blur
Color correction
add filter
Key frame time
ms
0%
0 px
-100%
+100%
100%
Original Size
-360°
-180°
-90°
0°
90°
180°
360°


Close
Properties
Animation
Pan (px)
add modifier
Zoom (px)
Rotate
Center
Framing
Opacity
Blur
Color correction
add filter
-100
0
100
-20
0
400

Framing

- Framing can be used to Pan and/or Zoom an Image within a Frame without modifying the frame itself
- Framing can also be used to adjust an Aspect Ratio mismatch

- In the example below a 4:3 image is shown within a 3:2 frame at 90% of full screen in a 16:9 Project.
- In the default 100% Scaling (S) the 4:3 Image has been “cut off” at the top and bottom of the Image and “Fits” the Width of the 3:2 Frame.



- By adjusting the “S”, “X” and “Y” Controls a “Best Fit” composition can be achieved
- Further Panning and Zooming is possible



Opacity and Blur

- The Illustration shows Main Image used as a Background Image at 100% Opacity and Zero Blur



- The following Illustration shows the same Background Image with reduced Opacity and a little

Blur



Modifiers

- Modifiers can be applied to an Animation of an Object / Image between two Key Frames
- The Modifier is applied to the first Key Fame of a pair of Key Frames defining the animation
- Click on “Modifier”



- The drop-down shows a number of options, the first being Animation Speed



- Acceleration - the animation starts “slowly” and builds up to a maximum
- Slow Down - the animation starts at maximum speed and finishes smoothly
- Smooth - Starts an ends smoothly, with the maximum speed in the middle
- Custom - Linear Acceleration to the Middle of the animation and Linear Deceleration to the finish - a starting point for a Custom Setting



- Pan, Zoom, Rotate etc all have a set of modifiers labelled:
  - Oscillation
  - Jumping
  - Ping Pong
  - Shift



- The following Video demonstrates the various Modifiers

Video

Colour Correction

- Click on “Add Filter” to display a list of available Colour Correction Adjustments:



The available Adjustments are:

- Levels
- Brightness / Contrast
- Hue / Saturation
- Toning
- Colouration
- Negative

Levels

- The Adjustments:



- Click and drag within the area outlined to the Left and / or Right to change the value of the adjustment
- Values can be entered directly via the keyboard
- Increasing the Black Point and decreasing he White Point will apply Contrast to the Object / Image
- Increasing / Decreasing the Midtones will Lighten / Darken the Object / Image

Brightness / Contrast

- The Adjustments:

- Click and drag within the area outlined to the Left and / or Right to change the value of the adjustment
- Values can be entered directly via the keyboard
- Drag to the Left / Right to Decrease / Increase Brightness
- Drag to the Left / Right to Decrease / Increase Contrast

Hue / Saturation

- The Adjustments:



- Click and drag within the area outlined to the Left and / or Right to change the value of the adjustment
- Values can be entered directly via the keyboard
- Drag to the Left / Right to change the Hue
- Drag to the Left / Right to Desaturate / Saturate the Object / Image
- Drag to the Left / Right to Darken / Lighten the Object / Image

Toning

- The Adjustments:
- Choose from Grayscale, Sepia or Cyan



- Click and drag within the area outlined to the Left and / or Right to change the value of the adjustment
- Values can be entered directly via the keyboard
- Click on the Colour /Grayscale to open the Choose Colour Box and change the Tone
- Drag the Amount Slider to the Left to Decrease the Effect

Colouration

- The Adjustments:
- Choose from Red, Green or Blue



- Click and drag within the area outlined to the Left and / or Right to change the value of the

adjustment
- Values can be entered directly via the keyboard
- Click on the Colour to open the Choose Colour Box and change the Tone
- Drag the Amount Slider to the Left to Decrease the Effect

Negative

- No Adjustments
- Creates a Negative version of the Object / Image
- Combine with Grayscale Toning or Desaturation to make a Black and White Negative from a Colour Image
- Can also be used for “Inverting a Mask” (with “Convert to Alpha Image” unticked)

Key-frame Time

- Allows for precise positioning of Key-Frames



From:
https://docs.pteavstudio.com/ - **PTE AV Studio**

Permanent link:
https://docs.pteavstudio.com/en-us/10.0/objectsandanimation_1/animation_tab

Last update: **2022/12/19 11:48**