


Animation Tab

The Animation Tab is shown below. This provides the various adjustments and parameters to control animation of objects.



- For Pan and Rotate, adjustments can be made in three planes
 - X,Y and Z for Pan
 - C,Y and X for Rotate
- These adjustments replace the 3D parameters provided in Version 8.
- A new adjustment called Framing is provided (see [Framing](#))
- The Color Correction parameters have been expanded in Version 9 ([Color Correction](#))
- The “Key Frame Time” box shows the time (in milliseconds) of the selected Key Frame

New In Version 11 - Smooth Move




- The Smooth Move Modifier can be used to create a Smooth path (Pan X;Y;Z) of an Object through three (or more) Key Frames with no pause or jump
- Apply the Modifier to Key Frames 1 and 2 etc
- Adjust the amount of Smoothing via the Smoothing % control

Parameter Controls

Display Mode for Pan and Zoom


Click on the “%” sign or the “100%” sign:

- “%” = Percentage Mode
- “px” = Pixels Mode
- “pt” = Original Points Mode
- “100%” = Full Height of Project Screen
- “Original Pixels” = The Original Pixel Size of the Image




The Illustration below shows a 640x480 rectangle at Original Size in a 1920x1080 Project


- In Percentage Mode:
- The values for "X" and "Y" Pan are calculated for the Centre of the Object/Rectangle with respect to the Centre of the Slide
- The value of the Zoom Parameter is the percentage of the Full Height of the Project Screen (in this case 1080 pixels)
- $480/1080 = 0.444444444444 = 44.444444444\%$



- In Pixels Mode:
- The values for "X" and "Y" Pan are calculated for the Top Left Corner of the Object/Rectangle with respect to the Top Left Corner of the Slide
- The value of the Zoom Parameter is the Pixel Size of the Object/Rectangle




- In Points Mode



The Centre Control


- The “CENTRE” Control can be used to move the CENTRE or “Point of Rotation” of an Object as

shown below:




The Rotate Control


- The “Rotate C” Control will rotate an Object about its Centre Point in the same plane as the screen:




- The “Rotate Y” Control will rotate an Object about its Centre Point in 3 Dimensions Horizontally:



- The “Rotate X” Control will rotate an Object about its Centre Point in 3 Dimensions Vertically:



- The “C”, “Y” and “X” Rotate Controls can be used simultaneously:



Changing Parameters with the Mouse

- Place the Mouse on any Letter (e.g. X,Y or Z in the Pan Controls) and click and drag left or Right
- You can also Right Click on any Letter and access commonly used Preset Values (See Right Click Menus below)
- You can “double click” on any letter to change the value back to its default state

Keyboard Entry

- In any box, highlight the existing value and type in a new value

OR Place the cursor in a box and:

- UP arrow on Keyboard increases the value by one unit
- DOWN arrow decreases the value by one unit
- Pg Up on Keyboard increases the value by ten units
- Pg Dn on Keyboard decreases the value by ten units

The UNITS depend on the chosen Display Mode:

- In % Mode the units will increase/decrease by 1% or 10% of the Parent Frame (or Background)
- In Px Mode the units will increase/decrease by 1 Pixel or 10 Pixels - relative to Project Size
- In Pt Mode the units will increase/decrease by 1 Pixel or 10 Pixels relative to the Original size of the Object

Pan

- The parameters can be read in Percentage, Pixels or Original Points

- X - Horizontal movement of the Object relative to the width of the Object's Parent Frame
- Y - Vertical movement of the Object relative to the height of the Object's Parent Frame
- Z - Zoom - "Closer to" or "further away from" the viewer


Zoom


- The parameters can be read in Percentage, Pixels or Original Points
- X - The horizontal dimension relative to the native size/resolution of the Object's Parent Frame
- Y - The vertical dimension relative to the native size/resolution of the Object's Parent Frame
- With the "Chain Link" deselected the object can be distorted
- With the "Chain Link" restored the distorted image/object can be scaled
- Shift + Click and Drag on the "bounding box" will temporarily "unlink" the X and Y parameters and allow the object to be "distorted"
- Click on 100% to return to default settings (100%)

The UNITS depend on the chosen Display Mode:

- In % Mode 100% = 100% of the Parent (Slide / Frame etc)
- In Px Mode the Pixel Dimensions of the Object are shown
- In Pt Mode 100% = 100% of the Native Pixels of the Object


The Right Click Menus for X, Y and Z






Framing

- Framing can be used to Pan and/or Zoom an Image within a Frame without modifying the frame itself
- Framing can also be used to adjust an Aspect Ratio mismatch
- In the example below a 4:3 image is shown within a 3:2 frame at 90% of full screen in a 16:9 Project.
- In the default 100% Scaling (S) the 4:3 Image has been “cut off” at the top and bottom of the Image and “Fits” the Width of the 3:2 Frame.




- By adjusting the “S”, “X” and “Y” Controls a “Best Fit” composition can be achieved
- Further Panning and Zooming is possible




Opacity and Blur

- The Illustration shows Main Image used as a Background Image at 100% Opacity and Zero Blur



- The following Illustration shows the same Background Image with reduced Opacity and a little Blur




Parameter Controls

Display Mode for Pan and Zoom


Click on the "%" sign or the "100%" sign:

- "%" = Percentage Mode
- "px" = Pixels Mode
- "pt" = Original Points Mode
- "100%" = Full Height of Project Screen
- "Original Pixels" = The Original Pixel Size of the Image




The illustration below shows a 640×480 rectangle at Original Size in a 1920×1080 Project


- In Percentage Mode:
 - The values for "X" and "Y" Pan are calculated for the Centre of the Object/Rectangle with respect to the Centre of the Slide
 - The value of the Zoom Parameter is the percentage of the Full Height of the Project Screen (in this case 1080 pixels)
 - $480/1080 = 0.444444444444 = 44.44444444\%$



- In Pixels Mode:
- The values for "X" and "Y" Pan are calculated for the Top Left Corner of the Object/Rectangle with respect to the Top Left Corner of the Slide
- The value of the Zoom Parameter is the Pixel Size of the Object/Rectangle




- In Points Mode




The Centre Control

- The “CENTRE” Control can be used to move the CENTRE or “Point of Rotation” of an Object as shown below:




The Rotate Control


- The “Rotate C” Control will rotate an Object about its Centre Point in the same plane as the screen:




- The “Rotate Y” Control will rotate an Object about its Centre Point in 3 Dimensions Horizontally:



- The “Rotate X” Control will rotate an Object about its Centre Point in 3 Dimensions Vertically:



- The “C”, “Y” and “X” Rotate Controls can be used simultaneously:



Changing Parameters with the Mouse

- Place the Mouse on any Letter (e.g. X,Y or Z in the Pan Controls) and click and drag left or Right

- You can also Right Click on any Letter and access commonly used Preset Values (See Right Click Menus below)
- You can “double click” on any letter to change the value back to its default state

Keyboard Entry

- In any box, highlight the existing value and type in a new value

OR Place the cursor in a box and:

- UP arrow on Keyboard increases the value by one unit
- DOWN arrow decreases the value by one unit
- Pg Up on Keyboard increases the value by ten units
- Pg Dn on Keyboard decreases the value by ten units

The UNITS depend on the chosen Display Mode:

- In % Mode the units will increase/decrease by 1% or 10% of the Parent Frame (or Background)
- In Px Mode the units will increase/decrease by 1 Pixel or 10 Pixels - relative to Project Size
- In Pt Mode the units will increase/decrease by 1 Pixel or 10 Pixels relative to the Original size of the Object

Pan

- The parameters can be read in Percentage, Pixels or Original Points
- X - Horizontal movement of the Object relative to the width of the Object's Parent Frame
- Y - Vertical movement of the Object relative to the height of the Object's Parent Frame
- Z - Zoom - “Closer to” or “further away from” the viewer



Zoom

- The parameters can be read in Percentage, Pixels or Original Points
- X - The horizontal dimension relative to the native size/resolution of the Object's Parent Frame
- Y - The vertical dimension relative to the native size/resolution of the Object's Parent Frame
- With the “Chain Link” deselected the object can be distorted
- With the “Chain Link” restored the distorted image/object can be scaled
- Shift Click and Drag on the “bounding box” will temporarily “unlink” the X and Y parameters and allow the object to be “distorted”
- Click on 100% to return to default settings (100%)

The UNITS depend on the chosen Display Mode:

- In % Mode 100% = 100% of the Parent (Slide / Frame etc)
- In Px Mode the Pixel Dimensions of the Object are shown
- In Pt Mode 100% = 100% of the Native Pixels of the Object

The Right Click Menus for X, Y and Z




Framing


- Framing can be used to Pan and/or Zoom an Image within a Frame without modifying the frame

itself

- Framing can also be used to adjust an Aspect Ratio mismatch
- In the example below a 4:3 image is shown within a 3:2 frame at 90% of full screen in a 16:9 Project.
- In the default 100% Scaling (S) the 4:3 Image has been “cut off” at the top and bottom of the Image and “Fits” the Width of the 3:2 Frame.




- By adjusting the “S”, “X” and “Y” Controls a “Best Fit” composition can be achieved
- Further Panning and Zooming is possible




Opacity and Blur

- The Illustration shows Main Image used as a Background Image at 100% Opacity and Zero Blur




- The following Illustration shows the same Background Image with reduced Opacity and a little

Blur




Modifiers

- Modifiers can be applied to an Animation of an Object / Image between two Key Frames
- The Modifier is applied to the first Key Frame of a pair of Key Frames defining the animation
- Click on “Modifier”



- The drop-down shows a number of options, the first being Animation Speed




- Acceleration - the animation starts “slowly” and builds up to a maximum
- Slow Down - the animation starts at maximum speed and finishes smoothly
- Smooth - Starts and ends smoothly, with the maximum speed in the middle
- Custom - Linear Acceleration to the Middle of the animation and Linear Deceleration to the finish - a starting point for a Custom Setting

The screenshot shows the Animation Tab interface with four expandable sections:

- Animation speed: Accelerate**: Contains fields for Accel. time (%), Decel. time (%), Start speed, and Final speed, all set to 56, 1, 0, and 0 respectively.
- Animation speed: Slow down**: Contains fields for Accel. time (%), Decel. time (%), Start speed, and Final speed, all set to 1, 56, 0, and 0 respectively.
- Animation speed: Smooth**: Contains fields for Accel. time (%), Decel. time (%), Start speed, and Final speed, all set to 26, 26, 0, and 0 respectively.
- Animation speed**: Contains fields for Accel. time (%), Decel. time (%), Start speed, and Final speed, all set to 50, 50, 0, and 0 respectively.


Smooth Move

- To use the Smooth Move modifier it necessary to have at least 3 keyframes and apply this modifier to the middle keyframe.
- It creates a Bezier curve for the motion.



Pan x; PanY; Pan Z

- Pan, Zoom, Rotate etc all have a set of modifiers labelled:
 - Oscillation
 - Jumping
 - Ping Pong
 - Shift




- The following Video demonstrates the various Modifiers



Colour Correction

- Click on “Add Filter” to display a list of available Colour Correction Adjustments:




The available Adjustments are:

- Levels
- Brightness / Contrast
- Hue / Saturation
- Toning
- Colouration
- Negative

Levels


- The Adjustments:



- Click and drag within the area outlined to the Left and / or Right to change the value of the adjustment
- Values can be entered directly via the keyboard
- Increasing the Black Point and decreasing the White Point will apply Contrast to the Object / Image
- Increasing / Decreasing the Midtones will Lighten / Darken the Object / Image

Brightness / Contrast


- The Adjustments:



- Click and drag within the area outlined to the Left and / or Right to change the value of the adjustment
- Values can be entered directly via the keyboard
- Drag to the Left / Right to Decrease / Increase Brightness
- Drag to the Left / Right to Decrease / Increase Contrast

Hue / Saturation

- The Adjustments:



- Click and drag within the area outlined to the Left and / or Right to change the value of the adjustment
- Values can be entered directly via the keyboard
- Drag to the Left / Right to change the Hue
- Drag to the Left / Right to Desaturate / Saturate the Object / Image
- Drag to the Left / Right to Darken / Lighten the Object / Image

Toning

- The Adjustments:
- Choose from Grayscale, Sepia or Cyan



- Click and drag within the area outlined to the Left and / or Right to change the value of the adjustment
- Values can be entered directly via the keyboard
- Click on the Colour /Grayscale to open the Choose Colour Box and change the Tone
- Drag the Amount Slider to the Left to Decrease the Effect

Colouration

- The Adjustments:
- Choose from Red, Green or Blue



- Click and drag within the area outlined to the Left and / or Right to change the value of the adjustment
- Values can be entered directly via the keyboard
- Click on the Colour to open the Choose Colour Box and change the Tone
- Drag the Amount Slider to the Left to Decrease the Effect

Negative

- No Adjustments
- Creates a Negative version of the Object / Image
- Combine with Grayscale Toning or Desaturation to make a Black and White Negative from a


Colour Image

- Can also be used for “Inverting a Mask” (with “Convert to Alpha Image” unticked)




Key-frame Time

- Allows for precise positioning of Key-frames



Colour Correction

- Click on “Add Filter” to display a list of available Colour Correction Adjustments:




The available Adjustments are:

- Levels
- Brightness / Contrast
- Hue / Saturation
- Toning
- Colouration
- Negative

Levels

- The Adjustments:



- Click and drag within the area outlined to the Left and / or Right to change the value of the adjustment
- Values can be entered directly via the keyboard
- Increasing the Black Point and decreasing the White Point will apply Contrast to the Object / Image
- Increasing / Decreasing the Midtones will Lighten / Darken the Object / Image

Brightness / Contrast


- The Adjustments:



- Click and drag within the area outlined to the Left and / or Right to change the value of the adjustment
- Values can be entered directly via the keyboard
- Drag to the Left / Right to Decrease / Increase Brightness
- Drag to the Left / Right to Decrease / Increase Contrast

Hue / Saturation

- The Adjustments:



- Click and drag within the area outlined to the Left and / or Right to change the value of the adjustment
- Values can be entered directly via the keyboard
- Drag to the Left / Right to change the Hue
- Drag to the Left / Right to Desaturate / Saturate the Object / Image
- Drag to the Left / Right to Darken / Lighten the Object / Image

Toning

- The Adjustments:
- Choose from Grayscale, Sepia or Cyan



- Click and drag within the area outlined to the Left and / or Right to change the value of the adjustment
- Values can be entered directly via the keyboard
- Click on the Colour /Grayscale to open the Choose Colour Box and change the Tone
- Drag the Amount Slider to the Left to Decrease the Effect

Colouration

- The Adjustments:
- Choose from Red, Green or Blue



- Click and drag within the area outlined to the Left and / or Right to change the value of the adjustment
- Values can be entered directly via the keyboard
- Click on the Colour to open the Choose Colour Box and change the Tone
- Drag the Amount Slider to the Left to Decrease the Effect

Negative


- No Adjustments
- Creates a Negative version of the Object / Image
- Combine with Grayscale Toning or Desaturation to make a Black and White Negative from a Colour Image
- Can also be used for “Inverting a Mask” (with “Convert to Alpha Image” unticked)



Key-frame Time

- Allows for precise positioning of Key-Frames

Last update: 2023/02/09 12:34
en-us:11.0:objectsandanimation_1:animation_tab https://docs.pteavstudio.com/en-us/11.0/objectsandanimation_1/animation_tab?rev=1675946077



From:
<https://docs.pteavstudio.com/> - PTE AV Studio

Permanent link:
https://docs.pteavstudio.com/en-us/11.0/objectsandanimation_1/animation_tab?rev=1675946077

Last update: **2023/02/09 12:34**

