Understand Full Slide Duration and KFSD

Full Slide Duration

Full Slide Duration refers to the length of time a slide is visible on screen.


An example:

- In Settings / Preferences / Project set your project up as shown below with "Show full slide duration" and "Keep full slide duration" ticked
- In Setings / Preferences / Toolbars / Status Bar Tick Slide Duration and Full Slide Duration

Preferences			
Editions	Save and recovery		
Project	Auto save project file every 10 🚔 minutes		
System	Project file		
Timeline	Load last project on startup		
Toolbars	 Hold time points after changes in the Slide list Show full slide duration 		
Editor	Default options for new slides		
Templates	Keep full slide duration		
	Scale key frames in objects (on time change)		
	Optimization of video clips Ask every time		
	Executable files for PC and Mac		
	Allow modification of slideshow EXE file		
	OK Cancel		

- In Project Options set a 10 second Slide Duration and a Zero second Transition Duration
- Drag four images into the Slide List

The Slide List View:




The Timeline View:

Project1 - PicturesToExe Deluxe					
<u>File Publish Project Slide Settings H</u> elp					
🗋 🚰 👻 🔚 👌 🦿 Comment 🗣 📧 Change Image File 🧶 Add Audio or Voice 💿 Preview 🛛 Publish Show					
Image: Windowski with the second					
0 0:10 0:20 0:30 0:40 1 1 0 0:20 0:30 0:40 1					
1. AU-wr 2. AU-wr 3. AU-wr 4. AU-wr					
Add audio files from a file list above					
Project Options Slide Style Objects and Animation X Slide 1 of 4 C Slides Timeline					
Slide 1 of 4 Full duration: 10.0 s Duration: 10.0 s 1800 x 1200 Z:\PTE\TEST OBJECTS\3x2\AU-wp1_1.jpg					

• The Information at the bottom of the screen shows that the Full Duration and the Duration are


- both 10s
- Slide 1 = 0 to 10s
- Slide 2 = 10s to 20s
- Slide 3 = 20s to 30s
- Slide 4 = 30s to 40s
- Add a Transition Duration of 2 seconds to Slide 2 using the AB button in the Slide View



- The 10s Full Slide Duration is retained for all slides
- Slide 1 = 0 to 10s
- Slide 2 = 8s to 18s
- Slide 3 = 18s to 28s
- Slide 4 = 28s to 38s

Add a 2s transition to all slides:

Last update: 2022/12/18 11:20



Keep Full Slide Duration

Note: If the setting of Keep Full Slide Duration is altered in the middle of a Project - ONLY new slides added to the Slides List will have the NEW SETTING. All previous slides will retain the Previous Setting.

There are two questions that need to be answered in order to explain Keep Full Slide Duration:

- "WHAT" is Kept?
- More importantly: "WHEN" is "it" Kept?

The first question is simple to answer: The Full Slide Duration is Kept.

The answer to the second question is a little more complicated.

Example 1:

- Here we see a Timeline with Four slides each with a Full Slide Duration of 10 seconds and 2 seconds Transition Duration
- The Keep Full Slide Duration was ticked when the slides were added to the Slide List so they are "KFSD Slides"
- Opening Slide Options for each individual slide will show the option "Keep full slide Duration" = Ticked

5/8

Project1 - PicturesToExe Deluxe					
File Publish Project Slide Settings Help	ge File 🥑 Add Audio or Voice 🕞 Preview Publish Show				
AU-wp3_1.jpg					
✓ Time points + = 00:26.001	00:34 5				
	0:30 0:40				
	4. AU-wr				
Add audio files from a file list above					
	Slides Timeline				
Project Options Slide Options Slide Style Objects and Animation X Slide 4 of 4 Full duration: 10.0 s Duration: 10.0 s 1620 x 1080	Slide 4 of 4				

• If we now go to the Slide List and change the Transition Duration of Slide 2 to 4s by means of the AB button the Full Slide Duration of all slides is retained or "Kept"

The Timeline View:

Last update: 2022/12/18 11:20

Project1 - PicturesToExe Deluxe				
<u>File Publish Project Slide Settings Help</u>				
🗋 🗁 🖛 👌 🦿 Comment 👻 📧 Change Image F	ile 🧶 Add Audio or Voice 📄 Preview Publish Show			
AU-wp3_1.jpg				
······································				
☑ Time points	00:32 5 2			
	0:30 0:40			
A. AU-wr				
Add audio files from a file list above				
	▼			
Project Options Slide Options Slide Style Objects and Animation X S	lide 4 of 4 🖉 🛆 Slides Timeline			
Slide 4 of 4 Full duration: 10.0 s Duration: 10.0 s 1620 x 1080 Z	\PTE\TEST OBJECTS\3x2\AU-wp4_1.jpg			

- Slide 1 = 0 to 10s
- Slide 2 = 6s to 16s
- Slide 3 = 14s to 24s
- Slide 4 = 22s to 32s

Please Note that changing Transition and/or Slide Durations by DRAGGING in the Timeline does NOT retain or Keep Full Slide Duration


Example 2:

- Using the last example I have added a Video to the Slide List between Slides 2 and 3 the duration of which is 35.602 seconds
- The Video is added as a Keep Full Slide Duration slide


The Slide List View is shown below

2025/08/02 13:43

7/8




The Timeline View:



The Full Slide Duration of all Slides is retained.

In the next image the Video is moved (IN THE SLIDE LIST View) from its position between slides 2 and

3 to a position between slides 3 and 4



Once again the Full Slide Duration of all slides is KEPT or Retained.

Please Note that changing Transition and/or Slide Durations by DRAGGING in the Timeline does NOT retain or Keep Full Slide Duration



Last update: 2022/12/18 11:20