Slide Styles

Introduction

A slide style is a template of animations with optional objects.

In most cases it is necessary for a Slide to have at least one "Main Image". However if the Style is designed appropriately then it can be applied to a Blank Slide.

A Slide Style also includes a Transition. e.g. If the Style creates multiple slides, each slide's transition can be determined in the Style.

For example, you can choose a Slide Style which creates "Pan Left" or "Zoom Out" animation and apply this Slide Style to one or more slides.

Preset Styles

The Style Slide button in the Bottom-Left Toolbar opens the Slide Style window. (See The Main Window and Main Menu/Preferences/Toolbars)

📶 Slide style			×
Basic	No Style	1 image	
Borders	Album	1 image	
Captions	Blur - Zoom In	1 image	
Experimental	Blur - Zoom Out	1 image	
lmage	Pan Down	1 image	
Wedding	Pan Left	1 image	
Album Pages	Pan Right	1 image	
DaveGee Windows	Pan Up Rotate - Zoom In	1 image 1 image	Information
Flying Images	Rotate - Zoom Out	1 image	Style needs 1 image. You chose 1 image
Masks	Slide Down	1 image	Speed 100 🐳 %
My Preset Styles	Slide Left	1 image	Full duration 7.000 🖨 s
Sliding	Slide Right	1 image	Options
Trial Styles	Slide Up	1 mage	Zoom 122 V %
User styles	Vignette - Zoom In	1 image	Pan X 0 1 %
	Vignette - Zoom Out	1 image	Pan Y 0 %
User styles	Zoom In	1 image	
V8 Style Test	Zoom Out	1 image	
Version 8	-		
Basic	-		
Diapositif	-		
Frames	-		
Tools			Apply Close

On the left hand side of the window we have the Slide Style Categories - Basic, Borders etc.

In the middle the Slide Styles in each category are listed. This also shows how many images are required to create the Style.

The image at the top right hand side is a Preview of what the Style will do.

Information

This tells the user how many Images are required and how many have been chosen (selected) in the Slide List. If the number of images chosen is not correct it will result in a Grey Image (or Images) in the Preview.

Duration

The Speed and Full Duration controls determine the Full duration of the Applied Style and are interactive. The Speed Control will increase or decrease the Full Duration of the Applied Style and the effect is shown in the Preview Window. The default is 100% = Full Duration of the Slide Style. Faster

Speeds will decrease the Full Duration and slower Speeds will increase the Full Slide Duration. You can type a specific time into the Full Duration box.

Note that the Slide Style Full Duration will overwrite the Full Duration of the slide that it is being applied to.

Options

Options will vary according to the Style.

Size is a static Zoom percentage applied throughout the duration of a Style. Zoom is usually the amount of Zoom applied dynamically through the duration of the Style. Another example is Border which sets the thickness of a Border as a percentage of the Image Height.

Author's Name and Comments

• Custom Transitions may contain the Author's Name and Comments regarding the use and any restrictions which apply to the Style

🚮 Slide style			×
Full Screen Borders	Framing Triptych Horizontal De	2 images	
Gliding	Framing Triptych Horizontal Uni	1 image	
lgor Tests	Framing Triptych Universal	1 image	
Jeff			
Menus			
Perspective			
Speed Visualizer			
Splitter			Information
Strips			Style needs 2 images. You chose 1 image
Test			Speed 100 🐳 %
Text			Full duration 24.000 s
TG			
Trips - Multi images			Author DaveGee
Tychs			16:9 Only - add two 16:9 Images
User styles			
Tools			Apply Close

Apply

The APPLY button creates the slide.

Applying a Preset Style

Please be aware that Applying a Style will overwrite any existing Animation. Slide Styles are NOT additive.

- 1. Open the Slide Style Window
- 2. Browse the Preset Styles to find the Style which you want to apply
- 3. Note how many images are required for the Style
- 4. Close the Style Window
- 5. Drag the correct number of Images in to the Slide List and/or.....
- 6. Highlight the correct number of Slides/Images
- 7. Open the Slide Styles Window
- 8. Highlight the required Style
- 9. Check that the preview shows the Style correctly
- 10. Make any changes that you require to the Duration and Option controls
 - Note that any change made to the Duration of the Style will also increase/decrease the Style's default Transition Time by the same percentage
- 11. Apply the Style

Creating Slide Styles

Not available in the Essentials Edition

Creating your own Styles


Any Slide (or Slides) to which animation has been added can be turned into a Style and saved in the User Styles Tab of Slide Styles. Highlight the Slide (or Slides) and open the Slide Style window by clicking on the Slide Style Tool. Click on the TOOLS button and select Create Slide Style.

Main Images

Styles use the "Main Image" concept (new in Version 8). When an image is dragged into the Slide List it is automatically assigned the Main Image Index of 1. See Objects and Animation / Properties Tab. An Image added to a blank slide in Objects and Animation requires that a Main Image Index is added manually.

Where a Style includes more than one Main Image, the images should be indexed 1, 2, 3, 4 etc during the creation process (Objects and Animation/Properties Tab/Main Object). Then, at the application stage, the Slide one Image is allocated to Main Image one in the Style etc. If an image occurs in the Style in more than one position, only the first instance needs to be Indexed - all other instances are "referenced". Example:

2025/08/02 14:47



Note that the image in Slide 2 is Indexed (Main Image 2) but that its reflection is not indexed.

When applying a Style which requires two (or more) images, they can also be added to a single blank slide in Objects and Animation and assigned Main Image Indexes 1 and 2 (etc). The Style can then be applied to that single slide containing two (or more) indexed images.

Non-Main Images

Styles can contain objects which are not Main Images.

Objects created in Objects and Animations such as Rectangles, Frames, Buttons, Masks etc are included in the Style as "instructions" and add very little in terms of file size.

If an Image is introduced in Objects and Animation (not designated as being Main Image) and used as a Background or to create an object such as a Box then that is also included in the Style but will increase the Style file size significantly. JPEGs and PNG files can be used for this purpose.

Project1 -	Create Slide style		×			1000	
File Publish	Slide style						
🗋 😅 🕶 🖡			V 🗵	Change Image File	Ø Add Audio or Voice	Preview	Publish Show
	Name	New Style					
	Category	Version 9	~				
•	category						
U	Author	Joe Bloggs					
	Comment	This Style will fly in, perform a triple somersault and crawl out.					
U	Aspect ratio of slides Any aspect ratio Use aspect ratio of this project - 16:9						
	Ontinent						
	Options						
	First slide	1					
U	Slide count	3					
	Number of slides for beginning	1					
	Number of slides for the end	1					
		1					
	Style duration	17.0 s					
						0	00:17 53
		Create Can	cel				00:17 23
AB 2.0	AB 2.0	AB 2.0					
	7.0	7.0 led-1920	3. Blank	.0			>
Project Option	s Slide Options Slide Style	Objects and Animation	x		Δ	Slides	Timeline
Selected: 3 of 3				Selected slides:	3		

Slide Style

- In the example above the Slide Style is given a Name
- Its Category can be either "User Styles" or typing a new category name will create a new Category. See the Dropdown Menu
- The Author can enter his name
- The Author can add comments about the Use of the Style and any specific requirements

Aspect Ratio of Slides

Users create projects which have different aspect ratios of slides (4:3, 16:9, etc). You have to declare the supported variants of aspect ratio for your style:

- If the animation in your style is simple you can choose 'Any aspect ratio' option
- Or you can choose fixed aspect ratio 'Use aspect ratio of this project 16:9'
- The second option is also used when making Multiple Aspect Ratio Variants of styles

You can create two independent styles - for 4:3 and for 16:9. Set the same name for both styles (for example, 'My style'). PicturesToExe will automatically combine both styles into one style. And users will see one style in the list. When the user applies this style PicturesToExe will automatically choose the correct variant (16:9 or 4:3) according settings of user's project. If the style does not contain the

necessary variant, PicturesToExe will choose the nearest variant (e.g. 4:3 for 5:4).

Styles Containing Several Slides

Adjust 'First slide' and 'Slide count' parameters to include the number of slides for the style.

Repeating Style

If you create a style which contains 3 slides and apply it to 6 slides it will be applied in the following order:

1,2,3,1,2,3 - because 'Number of slides for beginning' and 'Number of slides for the end' have a zero value.

A Style with a repeating Middle Part

Choose 3 slides, set 'First slide' as 1 and 'Slide count' as 3.

Set 'Number of slides for beginning' as 1 and 'Number of slides for the end' as 1.

Now this style will be applied to 6 slides in the following order:

1,2,2,2,2,3

- Slide 1 (of the Slide Style) will be applied to the first slide
- Slide 2 (of the Slide Style) will applied 4 times to slides 2,3,4,5
- Slide 3 (of the Slide Style) will be applied to last slide.

Example: Please download the following example of this application of a Style from the WNSOFT.com server

External Link

Import (see below) the Style and apply to three or more images dragged into the Slide List. The Style has "Beginning", "Middle" and "End" sections.

Add an Audio Clip to a Style


This is a workaround suggested by Igor:

- Add an invisible video clip with sound to a slide as an object. Pixel size should be very small to reduce CPU loading (say 160×120).
- You can create such a video file in PicturesToExe from a special project with your audio file.

Add a Text Comment to a Style

It is possible to add an editable text caption to a slide within a Style.

- Add a text object to a slide in Objects and Animation
- Right click on the text object to show the pop-up menu
- Choose Text Comment



- Create the Slide Style
- The Style will now have the parameter "Caption"

📶 Version 9 Menu File No Path -	- PicturesToExe Deluxe		-	
File Publish Project Slide	Settings Help			
🗋 🗃 🕶 🖬 👌 谢	🏪 C: 📧 ▼ 🛆	Comment 🛛 Terry & June's We 🗸 📧 Change Image File 🛛 Ø Add Audio or Voice	Preview	Publish Show
Na 🍃	A S	Slide style ×		
Untitled-11-Hi-Q.jpg	Untitled-11-Medium-Q	Captions Text Comment 1 image		
		Experimental		
	PAC.	Image Wedding		
Untitled-12-Hi-Q.jpg	Untitled-12-Medium-Q		ting	
	CA	DaveGee Windows	ing	/
	A.C.	Flying Images Information		
Untitled-13-Medium	Untitled-14-Medium-Q	Masks Style needs 1 image. You chose 1 image My Preset Styles Duration		
		Sliding Speed 100 🗘 %		
	1-00	Trial Styles Full duration 10.500 🜩 s		
Untitled-1920.jpg	wedding-ring_1920x120	User styles		00:17 53
AB 2.0	1	User styles Caption Terry & June's Wedding		
AD 2.0		V8 Style Test DaveGee		
		Album Pages		
Cerry & June's	r Wedding	Basic		
	10.5	Dianneitif		
1. Style Text Cor		Tools Apply Close		
<			Slides	Timeline
	Options Slide St	yle Objects and Animation x		
Slide 1 of 2 Full dur	ation: 10.5 s Dur	ation: 7.0 s 1920 x 1080 Style Text Comment		

Identifying a Style

If the Slide Name or Names are changed in Slide Options to a suitably descriptive name before Creating the Style then the Applied Slide Style will add an Identifier to the Slide or Slides.

Тір

Always save the Project from which you have made a Style as a Template for use at a later date.

Import a Slide Style

The Style ("xxxx.ptestyle") can be imported from any source.

- Click on Slide Style
- Click on Tools
- Click on "Import"

M Project1 - Pict	turesToExe Deluxe					- 🗆 🗙
File Publish P	📶 Slide style				×	
Unt	Basic Borders Captions Experimental	Sliding wth Transparency	2 images			y Publish Show
Unt	lmage Wedding					
	Album Pages			Information		
	DaveGee Windows			Style needs 2 images. You chose 1 image		
Unt	Flying Images			Duration		
	Masks			Speed 100 💉 %		
	My Preset Styles			Full duration		
	Sliding			Author		
	Trial Styles			DaveGee		
	User styles					00:17 53
AB 2.0	User styles					
	V8 Style Test					
	Create Style					
	Import Style Export Style					
	Change Style Catego Rename Style Delete Style	ory				7.0
	Tools			Арріу	Close	
Project Option:	s Slide Options	Slide Style Objects	and Animation	x 😰	Slides	Timeline
Slide 2 of 3	Full duration: 7.0 s	Duration: 5.0 s	1920 x 1080	405 KB Untitled-7		

Navigate to the source of the "ptestyle" file to be imported and highlight it and click on Open. The Style is then added to the User Category of Slide Styles or a Category specified by the author of the Style.

Export a Slide Style

In order to share User Styles or transfer them from your main Computer to your Laptop PC etc they first have to be Exported as "ptestyle" files.

- Choose the Style to be Exported
- Click on Slide Style
- Click on Tools

The Exported File is then saved in the folder designated in Settings / Preferences / Templates. This can be the default location or can be specified on a drive other than "c:" drive.


Any Non-Main Images in the Style are included in the Style - beware of the FILE SIZE of Non-Main Images!

Fonts - The Font used for any Text included in a Style is only honoured on another PC if it is present on the host PC. The "ptestyle" files can be uploaded to the PicturesToExe forum or sent in Personal Messages as "ptestyle" files. When sending in e-mail they should Zipped before attachment.

Change/Move/Create Categories

Change Category/Move to a New Style Category/Create a New Style Category

- You can create a New Style Category or rename any Category other than the Preset Styles Categories.
- From any other Category which you have created, the Change Style Category will Rename the Category.



The Right Click Menu

• To change the location or Category in which a Style is placed:

📶 Slide style				756	×
Basic	Blank		1 image	ACCOUNTS OF	
Borders	Blank 3x2		1 image		1000
Captions	Neustift		1 image	CT-sectores	and the second second
Experimental	Neustift 2 Neustift 2 UP	Import Style Export Style	je		
lmage		Change Style Category			
Wedding	Neustift 3x2 Ma	Rename Style	je	And	and a second second
DaveGee		Delete Style			
Lin's Styles				Information Style needs 1 image. You chose 1	l image
Neustift				Duration	-
PTE10				Speed	100 🚔 %
Tests				Full duration	9.000 🔹 s
Timers				Author	
Tutorial				DaveGee	
User styles		Change cat	tegory	×	
Version 9 Ty	pe new	Name of o	category		
	tegory Na	Ime Neustift			
			[Change Cancel	
Tools		L			Apply Close

Export a Category

• To Export a whole Category containing multiple Style - Right Click on the Category

Slide style			3
Full Screen Borders	Perspective Slide 1 L2R	1 image	
Gliding	Perspective Slide 1 R2L	1 image	
lgor Tests	Perspective Slide 2 B2T	1 image	
Jeff		-	
	Perspective Slide 2 T2B	1 image	
Menus	Perspective Slide 3 L2R	1 image	
Perspective	Perspective Slide 3 R2L	1 image	
Speed Visualizer	Import Style Export Category	6 images	
Splitter	Rename Category		Information
Strips	Delete Category		Style needs 1 image. You chose 1 image
			Duration
Test			Speed 100 🗘 %
Text			Full duration 12.000 🖨 s
TG			
Trips - Multi images	5		Author
Tychs		1	DaveGee
-			
User styles			
User Captions			
V9 Framing			
Version 9			
Tools			Apply Close

• Hotkeys for Styles: http://docs.pteavstudio.com/en-us/9.0/hotkeys/main#styles

