


The Publish Menu

The "Publish Show" Button

("Export Show")

If selected from "Settings/Preferences/Toolbars", a "Publish Show" button can be added to the Main Window toolbars. This provides further information on the "Publish" options and these are described below.



The Options are:

Executable File For PC

- Best Quality for PC in an EXE File (F9)
- Give the EXE a Name and Location and press Save.
- Double click on the Saved EXE to run.

Safe Executable File For Internet

- EXE File in ZIP with digital signature
- Give the EXE a Name and Location and press Save.
- The result is an Application and a digitally signed ptshow file in a Zipped Folder.
- This can safely be uploaded to a sharing site etc for Download. The Zipped File can be Extracted to a Folder in Windows and the slideshow can be run from the Application File.


HD and 4K Video

N.B. Since Version 9.0.5 PicturesToExe 9 supports Output of UltraHD 4K video (3840 x 2160). The 64-bit version of Windows is required for this resolution.

Publish a HD Video for playing on a Media Player (Shift+F2)


Creates high quality MP4 Video File (H.264)

The Project should be saved before clicking on the option - if you have not done this you will be asked to Save the Project.



The available options are shown above.

- Normal settings for TV playback are 1920×1080 and High Quality
- All of the presets work well
- Please be aware that some older TVs do not support 60p MP4




Clicking on Custom reveals further options:

Quality Mode - Set Quality 0-100

Bit Rate Mode - Set a Bit Rate

The Video File name is the same as the Project Name and the location will default to the same as the Project location.

Click Convert to start the encoding. The Progress Window is shown below:



When the encoding is completed you can view the video on a PC. Media Player Classic - Home Cinema is recommended for PC. You can also transfer the file to a USB device and view the video with the USB Device plugged into a suitably equipped Television or Blu Ray Player connected to a Television via HDMI.

DVD-Video Disc - Video Builder


- PTE 10 doesn't include VideoBuilder for DVD output by default.
- Because this app is 32-bit, doesn't offer Dark mode and we don't want spend time rewriting outdated app.
- So we will not declare official support for DVD output in PTE 10.
- However for compatibility and for needs of existing users we included VideoBuilder as add-on in Beta 29:
 - In the Main menu > Publish > click DVD-Video disc (Shift+F1) - (not in the Publish button menu)
 - PTE will offer download and install VideoBuilder in one click. It will take 5..20 seconds
 - Now DVD-Video output option will appear in the Publish button menu and in the main menu > Publish

For Players connected to a Television.


Click on Publish and DVD-Video Disc.

If the currently open project has not been edited since opening then you will be taken directly to the VideoBuilder interface. If the currently open project was created in an earlier version and not edited, it is recommended that you Save As a different version before entering the VideoBuilder.


If the currently open project was edited after opening then you will be prompted to Save the Project before continuing. You cannot proceed without saving so if you want to keep the original project intact then a Save As is required.



Add one or more Projects to the Project List by dragging from its location. The current project is added by default.



Click on (VideoBuilder) Project Options:




- In the above example the Menu Aspect Ratio (AR) and the TV screen Aspect Ratio have both been altered from the Default 4:3 AR.
- Repeat playback of a disc is possible
- Return to menu after each title is also possible
- Chapters can be added at any desired interval.
- You can Restore Defaults whenever necessary

In the Program Tab of (Video Builder) Project Options you can set

- Idle Priority
- Location of Temporary Folder
- Click OK to exit Project Options


In the Video Builder Main Menu you can set "Create Menu".

Click on "Next".



- You can “Choose Template” from several presets and/or add your own
- Items allows you to organize multiple Project Icons into a variety of Column and Row configurations
- Hue, Saturation and Lightness allows you to change the color of the chosen Template
- Properties allows you to alter the Position, Size and Opacity of the Project Icon.
- You can also add a Drop Shadow
- Select Frame allows you to choose a frame in the video to show in the Project Icon
- You can add a Background Image to replace the Template and Customize it
- You can choose to Animate the Menu and set the duration of the menu
- You can add music to the the Menu and Customize it

Click on “Next”



- You can give the Project a Name

You can select any of the following options:

- Create an MPEG2 file from the Project
- Create DVD Folders which can be burned to DVD in third party software
- Create an ISO File which can be burned to DVD in third party software (or played in Media Player Classic)
- Burn a DVD Disc. Details of your burner(s) and Speed of Burn are given.
- The DVD can be given a Label
- You can Include additional folders and files to the disc
- Click Start to begin the Burn

Add a User-Defined Template

In VideoBuilder:


- Tick the "Create Menu" box.
- In the Next Page, "Customize" an existing Template by adding your own Background Image in the Left Hand (Edit) section.
- Click on "Choose Template" and "Add a template" - Save in a suitable location with a suitable name and all of the components of the existing menu Template are saved with the renamed "bg.jpg" Background Image.
- It (the Template) then becomes a choice when you "Choose Template".
- An alternative method would be to "Add Template" first and then edit it by changing the Background etc. The Button Style is determined by the current chosen Template when the "Add

Template” is pressed.

- Buttons can be created and saved in the “New Template” folder. They must be named “Play” etc and overwrite the existing Buttons


Video For Mobile Devices

Creates a Video File for smartphone and tablets



The Preset Device Options (above):

- iPhone 5, 5s
- iPhone 6
- iPhone 6 Plus
- iPad (1024×768)
- iPad Retina (1920×1080)
- Tablet (1024×600)
- Tablet (1024×768)
- Tablet (1280×800)
- Tablet (1920×1080)
- Custom




The Preset Quality Options (above):

- High Quality
- Medium Quality
- Low Quality
- Pan and Scan (Enabled or Off)

AVI Video File


Creates AVI File with SD or HD Quality

The Presets:



The Presets for Resolution, Quality and Frame Rate are shown.

For the more adventurous, click on Custom:

 Creating AVI video file ✕

Creating a video file (in AVI MPEG4-ASP format) for PC, Mac, and any hardware player.
Recommended players for playback are: [Media Player Classic Homecinema](#), [VLC](#) and others.

Presets _____

Custom ▾

Pan Scan Disabled

Video _____

Width

1920 ▴ ▾

Height

1080 ▴ ▾

FPS

30p ▾

Mode

Quality ▾

Quality

70 ▾

☐ Motion Blur

Audio _____

Bit rate


256 ▾

Sample rate

44100 ▾

Video file name _____

D:\Documents\PROJECTS\Project1.avi



Preview

10 ▴ ▾

 s

OK

Cancel

Create HTML5 Video


From:

<https://docs.ptavstudio.com/> - **PTE AV Studio**

Permanent link:

https://docs.ptavstudio.com/en-us/10.0/main_menu_1/publish?rev=1568305213

Last update: **2022/12/19 11:45**



<https://docs.ptavstudio.com/>

Printed on 2025/09/12 07:27