Timeline View

See also the Audio Tab in Project Options.

Audio Files can be dragged and dropped into the Timeline tracks from the Files List.



Note that the position (time) of the added audio file is determined by the "drop" action.

The corresponding Project Options / Audio Tab looks like this:



Note that the "Offset" value for the audio file in Track 2 in the above example is from 0 seconds on the Timeline. The "Offset" value for the second audio file in Track 1 would be calculated from the end of the first audio file in Track 1. Fade Ins and Fade Outs made via the Envelope Function are not reflected in the Project Options / Audio Tab.

Other Controls in the Timeline View

🜠 Or	nline Helj	o Projecti	2 - Pictur	esToExe	Deluxe (64	4-bit)								- 0	×
File F	Publish	Project	Audio	Slide	Settings	Help									
	-		5		🚍 D:	Ømment		🖸 📧 Chang	e Image F	ile 1	Add Aud	dio or Voice	💌 Preview	v Publisl	h Show
*	Images 9200 D750						Î								
> ~	Favor Mich MP4	urites ael ne Help Ir	nages	l									4		
>] >] >]	Auc Auc Scans Sony Test Music Picture PTE Temp	lio udio Clip: s RAW :s	s			Audio Clips							2		
> > 	Z Pavil Z XP BD-RE D	ion rive (E:)		Ţ	01. E	scapulindo.mp3									
🗹 Tin	ne point:	+	- [0:00.000			≡• ▶■	00:05.02	9 —	_	•			00	:22 💱
0 0: 1	01 0:0	02 0:0	13 0:04	twirl	5 0:06 2	0:07 0:08	0:09 0:10 0	11 0:12	0:13	0:14 	0:15 0: 4	16 0:17	0:18 0:19	0:20 0:21	0:2
01. Esca	apulindo	.mp3	ala fan yn belle		4	nda billa, danta jan dara					en a fanskile.	ر میں	lest, satiss, be l	abbah, carab	الساد
4								(Clinton	Timel	*
Proj	ject Opti	ons	Slide	Option	<u>-</u>	Slide Style	Objects and A	nimation	× [_			Sildes	Timeli	ic .
Slide 2	of 4		Full dur	ation: 7	.0 s	Duration: 5.0			2.931	MB	02:33	D:\Imag	es\Online Help	Images\Audio\	01. Escapu

In the image above, from left to right:

- Time Points Toggles the Slide Numbers (1,2,3 etc) on or off
- + (Plus) Adds a Time Point at the Cursor Position

- (Minus) - Cuts the last Time Point in the Timeline to a position beyond the end of the Audio Tracks

- The time shown is the start time of the Slide under the cursor it is possible to fine tune the start time using up and down controls or by typing in the box
- The Envelope Icon Toggles the Envelope on or off in all tracks

Timeline Options

■ ▼ ▶ ■ 00:02.066									
Fit All Slides to Soundtrack									
Arrange Selected Slides									
Cut All Transition Points	Alt+Ctrl+H								
Shift Transition Points	Ctrl+E								
Set End of Last Slide at End of Soundtrack									
Export Soundtrack to File	Alt+E								

- The "triple horizontal line" (Timeline Options) Icon brings up the menu shown above
- Fit All Slides to Soundtrack adjusts the time of each equally and fits them to the soundtrack time
- Arrange Selected Slides select a group of slides and arrange them equally spaced
- Cut All Transition Points moves all transition points to a point beyond the end of the soundtrack
- Shift Transition Points select one or more slides and move their transition point(s) by a fixed amount
- Set End of Last Slide at End of Soundtrack useful for synchronizing the end of the last slide with the soundtrack
- Export Soundtrack to File Choose WAV, or MP3 and Bit Rate

The Timeline Right Click Menu - Audio Clips

Mute Track	Ctrl+N
Lock Track	
Lock All Tracks	Ctrl+L
Remove Track	
Move Track Up	Ctrl+PgUp
Move Track Down	Ctrl+PgDr
Link Audio Clip To Slide 6	
Remove Audio Clip	De
Duplicate Audio Clip	
Split Audio Clip	
Clear Audio Keypoints	
Customize Audio Clip	
File Info	

- Link Audio Clip to Slide x -
- Remove Audio Clip
- Duplicate Audio Clip- This command will duplicate the selected Audio Clip in a new Audio

Track

- Split Audio Clip This command will split the selected Audio Clip at the position of the cursor
- Clear Audio Keypoints
- Customise Audio Clip
- File Info

The Timeline Right Click Menu - Video Clips

Copy Slide	Ctrl+C
Paste Slide	Ctrl+V
Insert Blank Slide	Alt+S
New Transition	
Remove Slide	Del
Cut Transition	
Clear Slide List	
Random Order	Alt+R
Slide Options	Ctrl+U
Styles and Themes	
Objects and Animation	Ctrl+B
Rotate Clockwise	Ctrl+F
Rotate Counterclockwise	Alt+F
Audio Comment	>
Change Video File	Alt+C
Separate Audio from Video	
Trim Beginning of Video	
Export Slides to Images	
Edit File	Ctrl+W
File Info	Ctrl+1

Separate Audio from Video

- The Audio of a Video Clip is extracted from the Video Clip and is inserted into a New Track and can be edited as a normal Audio Track.
 - $\,\circ\,$ The Audio which remains in the Video Clip is automatically Muted

Trim Beginning of Video

• The video is trimmed to the position of the cursor. Note that the complete video clip is included in an EXE File. This option is best for MP4 output.

Scaling the Timeline View



The Mini Player

- The PLAY button starts the MINI-PLAYER from the Cursor Position
- The STOP Button stops the Mini-Player and returns the Cursor to the previous position
- The time shown at the end of the progress bar shows the End of the Last Slide
- The Four Arrow Icon starts the Full Screen Preview from the Cursor Position

Fade In / Fade Out Brackets

• In the Timeline, an Audio Clip can be faded in or out by means of the Fade In/Out Brackets at the beginning and end of the clip.



• By dragging the bracket along the Timeline a Fade is created:



- The Fade In and Out values are reflected in Project Options / Audio
- Likewise, a Fade In or Fade Out value entered in Project Options / Audio is reflected in the position of the Fade In / Out Brackets in the Timeline

Images

• Dragging images into the Timeline View is NOT advised. This is best done in the Slide List View. The DROP point overrides the Project Options / Slide Duration default and can lead to confusion.

From: https://docs.pteavstudio.com/ - **PTE AV Studio**

Permanent link: https://docs.pteavstudio.com/en-us/11.0/main-window_1/timeline_view?rev=1699616417

Last update: 2023/11/10 11:40

