Opzioni progetto

Scheda Principale

Generalità

La scheda "Principale" è mostrata di seguito:

📶 Opzioni proge	tto				×
Principale	Aspect ratio				
Audio	Aspect ratio	16:9	-		
Controllo	Temporizzazione				
Transizioni	Durata predefinita diapostiva	5.0 * s	Applica a tutte le	dia	
Schermo	Sfondo				
Predefinite	Colore pieno				
Avanzate	Gradiente				
	Colore intorno alla diapositiva				
				ОК	Annulla

- "Aspect Ratio" permette di selezionare l'aspect ratio desiderato dello schermo del monitor. Gli utenti devono considerare i parametri dello schermo principale per la presentazione quando selezionano aspect ratio.
- "Temporizzazione" permette di impostare il tempo predefinito per tutte le diapositive e può essere applicato a tutte le esistenti diapositive. Un'utile tecnica per certi tipi di presentazione è iniziare con una durata standard e poi modificare i tempi di singole diapositive per adeguarle alle specifiche esigenze.
- "Sfondo" permette all'utente di specificare il tipo e/o il colore dello sfondo per tutte le diapositive.

Aspect Ratio

Aspect Ratio delle immagini

L'aspect ratio delle immagini delle attuali fotocamere sono in genere:

- 3:2 Tipicamente 3000×2000; 6000×4000
- 4:3 Tipicamente 1024×768; 1600×1200; 4000×3000
- 16:9 Tipicamente 1920×1080

Aspect Ratio dei monitor

- 4:3 Tipicamente 1024×768; 1440×1080; etc
- 16:9 Tipicamente 1280×720; 1920×1080; etc
- 16:10 Tipicamente 1280×800; 1920×1200; etc

Aspect Ratio del progetto

Tipicamente, viene scelto per adattarsi all'aspect ratio di:

- Aspect ratio delle immagini delle fotocamere
- Monitor del PC dell'utente
- TV dell'utente (Tipicamente 1920×1080 al momento di stesura di questo documento)

Adattare queste scelte è talora difficoltoso per il principiante. Se si vuole facilmente inserire le immagini della fotocamera in una presentazione senza eseguire alcun ritaglio, l'Aspect Ratio per il progetto viene scelto per adattarlo alle immagini della fotocamera. Questo può comportare che nella presentazione compaiano delle "barre nere" ai lati o in alto e in basso nel monitor o nella TV.

Se si vuole che la propria presentazione riempia lo schermo del proprio monitor o della TV allora si deve scegliere l'Aspect Ratio adatto. Questo può determinare che le immagini della fotocamera non riempiano la larghezza del progetto o che vengano tagliate nella parte superiore e inferiore dello schermo.



L'esempio precedente mostra la vista a schermo intero (da sinistra a destra) di:

- Un'immagine 4:3 in un progetto 4:3 su uno schermo 4:3
- Un'immagine 3:2 in un progetto 3:2 su uno schermo 4:3
- Un'immagine 16:9 in un progetto 16:9 su uno schermo 4:3





L'esempio precedente mostra la vista a schermo intero (dall'alto in basso) di:

- Un'immagine 4:3 in un progetto 4:3 su uno schermo 16:9
- Un'immagine 3:2 in un progetto 3:2 su uno schermo 16:9
- Un'immagine 16:9 in un progetto 16:9 su uno schermo 16:9

Quale scelta fare?

Per il principiante, un punto di partenza potrebbe essere impostare l'aspect ratio del progetto uguale all'aspect ratio delle immagini della fotocamera. Le immagini possono così essere inserite in un progetto senza doverle modificare ed è possibile pubblicarle subito come file EXE senza ulteriori regolazioni. Quando l'utente diventa più esperto potrebbe essere più attraente la scelta dell'aspect ratio che si adatta al dispositivo di visualizzazione (Monitor/TV).

Scheda Audio

Aggiungere file audio

In Opzioni progetto / scheda Audio

Contract of the second	Aggiungi traccia Aggiungi file audi	io 🥕 🗙	• 00:00	03:5
\udio	Tracci	3:54	Durata originale	3:53.27
Controllo	\Oh nammamia! - Nducc o e Mimm	o Locasciulli.r 3:53	🗌 Collega a diapositiva	
ransizioni			Offset	0:01.500
chermo			Inizio	0:07.500
redefinite		×	Durata	3:53.279
vanzate	1 2		Dissolvenza in apertura	2.5
			Dissolvenza in chiusura	9.0
	3		Volume (%)	85 ~
			Durata colonna sonora	3:54.77
	1		Durata colonna sonora	3:54.77
	4		Durata colonna sonora Ripeti colonna sonora Converti tracce in MP3	3:54.77 per EXE

Il seguente esempio mostra una tipica semplice configurazione per Opzioni progetto / scheda Audio:

Principale	Aggiungi traccia Aggiungi file audio 🥕 🗙 🕩 00:0	00:32
Audio	Traccia 1 3:54 Durata o	riginale 4:12.14
Controllo	\Oh mammamia! - Nduccio e Mimmo Locasciulli.r 3:53	ega a diapositiva 🛛 2 📑
Transizioni	Traccia 2 0:39	0:02.000
Schermo	Inizio	0:05.500
Predefinite	Durata	0:32.396
Avanzate	Dissolver	nza in apertura 1.5 🚔
wanzate	Dissolver	nza in chiusura 7.5 📮
	Volume	(%) 75 ~
	Durata c □ Ripet ☑ Conv	olonna sonora 3:54.77 ti colonna sonora verti tracce in MP3 per EXE
	100	Bit rate 256 V

Il file audio nella Traccia 2 dispone delle seguenti proprietà:

Il pulsante PLAY riprodurrà il file audio di 32 secondi nel file audio evidenziato con lo scopo di provarlo

La Durata originale del file è 4m 12.143s

Il file audio nella Traccia 2 è collegato alla diapositiva 2 e se la diapositiva 2 è riposizionata anche il file audio verrà spostato dello stesso intervallo di tempo nella Timeline (traccia separata).

(N.B. Quando un clip audio è inizialmente collegato a una diapositiva la sua posizione deve essere regolata manualmente usando il controllo "Offset" - o trascinato nella Timeline).

Il file audio è Offset di 2s rispetto all'inizio della diapositiva 2 alla quale è collegato

L'Inizio del file audio nella Traccia 2 è 5.5s dopo l'inizio del file originale

La Durata del file audio è stata tagliata a 32.396s

Una Dissolvenza in apertura di 1.5s è stata applicata al file audio nella Traccia 2

Una Dissolvenza in chiusura di 7.5s è stata applicata al file audio nella Traccia 2

La Durata colonna sonora è calcolata in 3m 54.779s

Rinominare le tracce

Una traccia può essere rinominata e/o definita come una "Traccia per commenti audio"



Convertire le tracce in un file MP3 per EXE

When this option is turned on, PicturesToExe automatically converts all audio tracks to a single MP3 audio for the EXE show. The Bit Rate of the converted file can be adjusted from 64 to 320Kbps. High values are better quality.

This option is useful if you work with audio clips in WAV format or adjust the duration of clips using the Envelope Function. See Envelope. For maximum efficiency when using this feature the use of WAV files is advisable, though not essential.

This option will optimize the size of the EXE file.

Raccomandazioni per il formato MP3

When preparing MP3 Audio files for use in PicturesToExe the following is recommended:

- Constant Bit Rate 128 256 Kbps
- Sample Rate: 44100 Hz
- Stereo

Aggiungere/Estrarre l'audio di ub clip video in una traccia audio

The Audio of a Video Clip can be added to an Audio Track and the Envelope can then be applied to it. Add the Video Clip by dragging into the Slide Line and then, in Objects and Animation/Properties Tab, Mute the Audio of the Video Clip.

To add the Audio of the Video Clip to a Track go to Project Options / Audio Tab and Add a Track and then Add Audio File. In the bottom right corner of the browser change the "Audio Files" drop-down type to "Video Files" and navigate to your Video Clips Folder. Select your Video Clip and click on OPEN. Click OK in Project Options to see the Audio of the Video Clip in its Track. The envelope of the Audio of the Video Clip can then be adjusted as required.



Aggiungere audio o commenti vocali

Audio Clips and/or Voice Comments can be added to a Slide using the "Add Audio or Voice" Tool or by clicking on the "Microphone" icon in the Project Options/Audio Tab.



Click on "Add Audio File" to browse for the required Audio File and clicking on "Open" adds the file to an empty track. It can then be positioned and its envelope adjusted as required.

Click on "Record Voice Comment" to see the following:

Record	Stop
0:00	.000
Z:\PTE\TEST OBJECTS\	
Z:\PTE\TEST OBJECTS\ Comment5.mp3	Browse
Z:\PTE\TEST OBJECTS\ Comment5.mp3 Parameters	Browse

Click on Parameters to make adjustments to the File Type etc

Last update: 2022/12/18 11:20 it-i	it:9.0:project-options:main https://c	ocs.pteavstudio.com/it-it/9.0/p	project-options/main?rev=1489388786
------------------------------------	---------------------------------------	---------------------------------	-------------------------------------

Codec:	MP3				
Channels:	Mono				
Bit rate:	128 kbps 🗸				
Frequency:	44100 Hz -				
Record Device:	Primary Sound Capture Driver				
Back to Recording	L.				
	at and and				

- You can choose to record as MP3 or WAV
- You can choose Mono or Stereo recording
- You can choose Bit Rates from 32 to 320kbps
- The Recording device will vary according to the users system

When finished you can return "Back to Recording".

Click on "Record" to start the recording and "Stop" when finished. The Voice Comment is added to an empty track.

Time points	+ -	0:11.4	37 🚔 [~	≣		00:13	384 🥅									
0 0:01 0:02	0:03 0:0	4 0:05 (0:06 0:07	0:08 0:09	0:10	0:11 0:1	2 0:13	0:14	0:15	0:16	0:17	0:18	0:19	0:20	0:21	0:22	0:23 0:
								Real Providence	2								
						• 2	Comm	ent5.mp	3	~	~		•	•			
	Linke	ed to	Slide	2													
*																	
Publish Sh	ow	Project Opt	ions	Slide Option	ns	Slide St	yle	Obje	ects and	d Anim	ation) P	review			Slide	2 of 2
Slide 2 of 2	Fu	Il duration:	9.495 s	Durati	on: 9.495	5 s	1620) x 1080	1.	21 MB							

It is also possible to record the Voice Comment in "real time" while the Mini-Player is running or in the Audio Tab of Project Options.

Also see The Timeline View

Scheda Controllo

The "Control" tab with its 4 sections is shown below :

Project Option	s		×
Main	Show settings		
Audio	Action after the last slide	Close show	•
Control	Keyboard		
Transitions	Wait for a key press (Space o	r Right key) to show ne	ext slide
Screen	Mouse	, Keyboard	
Defaults	Exit on mouse move		
Advanced	Mouse wheel for rewinding		
	Left mouse button	No action	•
	Right mouse button	Next slide	•
	Mouse cursor	Show	▼ 3 ▲ s
	Navigation		
	Show Navigation Bar	Customize	
Customize	Navigation Bar		×
Style	Video player	-	Previous slide
🗹 Auto	hide	3 🔹 s	Next slide Exit
Fade in		200 🛉 ms	
Fade ou		300 🔽 ms	
	-	9 ~	
	_		
	-		00:00/00:00 🖣
<			
			OK Cancel
			OK Cancel

Show Settings

Mouse

The second section deals with mouse actions. These settings are independent of the "Keyboard" settings.

Mouse					
Exit on mouse move					
Mouse wheel for rev	vinding				
Left mouse button	No action	7			
Right mouse button	Next slide	•			
Mouse cursor	Auto hide	•	3	*	s

Various alternative actions are available. Most of these should be self-explanatory. The "mouse wheel for rewinding" allows the show to be re-wound when in the play mode.

Barra navigazione

The last section controls operation of the "Navigation Bar". If "Show Navigation Bar" is selected, an additional dialog box shown below opens when the "Customize" button is clicked and a navigation bar opens on screen during playback. This enables the user to perform various operations as specified in the customize dialog box. Note that the show needs to be set to "wait for keypress..." or individual slides set to "wait for keypress to show next slide", if a manually operated slide show is required.

PTE AV Studio - https://docs.pteavstudio.com/

• Action after last slide:

- Close Show
- Repeat Show
- Stop Show

Tastiera

The "Keyboard" section:

- Wait for key press Selecting this option enables a show to be controlled manually and applies to the whole show. An alternative method is to use the settings in "Slide Options/Main", but note that this applies to individual slides only. Note also that this option works whether the second option is selected or not.
- Permit control of show using keyboard This second option is provided to enable the user to override the default time of individual slides. For example the slide duration may be 10s. By selecting this option the next slide in the Slide line can be made to appear before the 10s has elapsed.

For many shows, it is likely that a user would leave these two options un-selected.



Scheda Transizioni

The "Transitions" tab is shown below with one of the various types of transitions selected to show the range of controls which can be applied to each transition. The range of parameters which can be controlled varies with the type of transition selected. The default transition is "Dissolve". At the top righthand side is a viewer which shows the effect of the transition selected.

Project Options		×
Main Audio Control Transitions Screen Defaults Advanced	Global transitions	
	 Curling of page 3D transitions Advanced Custom transitions Custom transitions 	Common options Transition effect duration 3.5 Thickness of smoothing line 35 Directions Variants Image: Image
	Manage transitions	OK Cancel

See also:

Custom Transitions

Scheda Schermo

The "Screen" tab with its 3 sections is shown below :

Last update: 2022/12/18 11:20	it-it:9.0:project-options:main https://docs.pteavstudio.com/it-it/9.0/project-options/main?rev=1489388786
-------------------------------	---

📶 Project Optio	ns		×
Main	Screen		
Audio	Mode	Fullscreen 👻	
Control	Sharpness control		
Transitions	Unsharp mask	None ▼ 0 ∨	
Screen	Watermark		
Defaults	Show watermark		6
Advanced	Offset	20 V Right-Bottom	~
	Opacity	100 ~	
	Size	30 ~	
		ОК	Cancel

Modo

2025/08/29 16:23

Project Option	15		×
Main	Screen		
Audio	Mode	Fullscreen	•
Control	Sharpness control	Fullscreen Fullscreen. Fixed size	
Transitions	Unsharp mask	Windowed with borders Windowed without borders	
Screen	Watermark		_
Defaults	Show watermark		6
Advanced	Offset	20 V Right-Bottom	*
	Opacity	100 ~	
	Size	30 🗸	
		ОК	Cancel

Unsharp Mask

Last update: 2022/12/18 11:20	it-it:9.0:project-options:main https	s://docs.pteavstudio.com/it-i	it/9.0/project-options/main?r	ev=1489388786
-------------------------------	--------------------------------------	-------------------------------	-------------------------------	---------------

📶 Project Optio	ns	>
Main	Screen	
Audio	Mode	Fullscreen 🔻
Control	Sharpness control	
Transitions	Unsharp mask	None
Screen	Watermark	None Best for static
Defaults	Show watermark	Best for animation
Advanced	Offset	20 V Right-Bottom T
	Opacity	100 ~
	Size	30 ~
		OK Cancel

Filigrana

• Add a Watermark

This enables the user to add a watermark to all images. If the option is selected, a dialog box as shown below will open and enable a watermark file to be chosen and the size and location on each image determined.

2025/08/29 16:23

istomize Water	mark 🗾 🔀
Position	Right-Bottom
Opacity	100 💌
Size	30.0
Offset	20 💌
	OK Cancel

Scheda Predefiniti

This Tab is not available in the Essentials Edition.

The "Defaults" tab with its 2 sections is shown below :

Project Options		×
Main	Text comment for new slides	
Audio	Customize font Insert template	
Control		
Transitions		
Screen		
Defaults	Apply to all slides	
Advanced	Main image for new slides	
	Display shadow behind slide image Customize	
	Apply to all slides	
	100 V % of the slide to show main images	
	Apply to all slides	
	Cover	
	Apply to all slides	
	OK Cancel	1
	OK Cancel	

Testi di commento per nuove diapositive

This provides a facility to insert text into slides and control the text formatting. The normal practice is to click on the "Insert template" button and choose the text required to be inserted. The code for this text will then appear in the box below the "Customize font" button. Additional text items can be added if required. When all the text items have been added, clicking the "Customize font" button will reveal the dialog box shown below and the added text can be formatted as required. A comment is required regarding the point in time at which this setting is applied. If applied BEFORE any slide have been added to the Slide list, then the text additions will apply to all slide subsequently added. If however this setting is selected AFTER slides have been added, then the "Apply to all slides" button must be clicked to ensure that the change is applied to all the currently added slides. Note also that if the user wishes to remove the added text, it is necessary to go into the dialog box, deleted the text and then click the "Apply to all slides" button to remove the text from all added slides.

Arial	•	
BIU	Color	
Center 🔹		Position on a slide:
Line spacing	0 🔻	Тор 🔻
Offset	3 💌	llext comme
Size	4.0 💌	Tant
Apply to a	ll slides	lext

Immagine principale per nuove diapositive

- If "Display shadow behind slide image" is selected, the "Customize" button will allow the parameters of the shadow to be selected, e.g. color/size/shape etc.
- The next control affects the size of the slide ; if the slide size is 100% then no shadow will be seen. Note also that this control can be used in conjunction with the "Screen/Background" tab to control the background color on which the slide appears. The "Apply to all slides" button should be used as described previously to apply the changes to all slides already inserted into the Slide line.
- The "Cover Slide" tick box allows this option to be set as the default for new images in the Project. If left unticked the "Fit to slide" option is set for the Project. The "Apply to all slides" button should be used as described previously to apply the changes to all slides already inserted into the Slide line.

The "Cover Slide" tick box added to Project Options from Version 8.0.17 onwards

Scheda Avanzate

This Tab is not available in the Essentials Edition.

The "Advanced tab with its 3 sections is shown below :

Project Option	5	×
Main	Protection of slideshow	
Audio	Ask for Password	
Control	Time limited usage Show settings	
Transitions	Advanced options	
Screen	Custom windows Show settings	
Defaults	lcon for executable file	6
Advanced	Synchronize soundtrack and slides	
	Pause when slideshow window becomes inactive Run application or slideshow on exit Do not run	
		OK Cancel

Protezione della presentazione

📶 Project Options			х
Main	Protection of slideshow		î
Audio	Ask for Password		
Control	Time limited usage	Hide settings	
Transitions	Expire after	30 days	
Screen	Number of runs	10 📄 times	
Defaults	Expire date	1 2109	
Advanced	Marrage	Month Day Year	
Advanced	Message	sorry, but that period of this show has expired	
	Advanced options		┛
	Custom windows	Show settings	
	lcon for executable file	<u>്</u>	
	Synchronize soundtrack an	nd slides	
	Pause when slideshow win	dow becomes inactive	~
		OK Cancel	

Opzioni avanzate

Project Options			\times		
	Time limited usage	Hide settings	^		
Main	Expire after	30 days			
Audio	Number of runs	10 times		Customize Windows	×
Control	Expire date	1 🔹 1 🔹 2109 🔹		Help window	
Transitions		Month Day Year		✓ Show help on F1 keypress	
Screen	Message	Sorry, but trial period of this show has expired		Custom windows	
Defaults	Advanced options			Add Customize	×
Advanced	Custom windows	Show settings			*
	Icon for executable file		6	Window name	
	Synchronize soundtrack and	d slides	_	Pause when this window is shown Use this window is shown	
	Pause when slideshow wind	low becomes inactive			
	Run application or slideshow on e	exit		01	
	Do not run 🔻		6	OK Cance	
			~		
		ОК	Cancel		

• Assign icon for executable file: This allows the user to select an icon from those stored on their computer or from an icon which has been created. The chosen icon will be associated with any

exe file created from Pictures To Exe

- Synchronize soundtrack and slides: It is recommended that this option is ALWAYS selected. If not, when playing a show from part the way through, the associated audio tracks will start from the beginning whereas the slides will start from the chosen position;
- Pause when slideshow becomes inactive: If selected, the slideshow will pause in its execution if the focus is moved to another application which is running.

Avviare una applicazione o una presentazione all'uscita

Project Options		×
Main	Protection of slideshow	
Audio	Ask for Password	
Control	Time limited usage Expire after	Hide settings
Transitions Screen	Number of runs	10 🕂 times
Defaults	Expire date	1 1 2109 Month Day Year
Advanced	Message	Sorry, but trial period of this show has expired
	Advanced options Custom windows I con for executable file	Show settings
	Synchronize soundtrack and Pause when slideshow wind	d slides dow becomes inactive
	Run application or slideshow on a Do not run Run Application Run Slideshow	
		OK Cancel

Assegnare un'icona al file eseguibile

This allows the user to select an icon from those stored on their computer or from an icon which has been created. The chosen icon will be associated with any exe file created from Pictures To Exe;

Sincronizzare colonna sonora e diapositive

It is recommended that this option is ALWAYS selected. If not, when playing a show from part the way through, the associated audio tracks will start from the beginning whereas the slides will start from the chosen position;

Pause when slideshow becomes inactive

if selected, the slideshow will pause in its execution if the focus is moved to another application which is running.

The second section "Protection of slideshow", provides 4 setting options. The intended function of these options is to assist users who wish to use PicturesToExe for commercial purposes.

Time limited usage

This enables a limit to be placed on how long a Pictures To Exe application can be run. If selected a dialog box opens which allows various expiry options to be selected.

Expire date	Month Day Year 1 1 2109 1 1 2109 1]
Expire after	30 days	_
Number of runs	10 times	
Expiration message	Sorry, but trial period of this presenta	tion has exp

The final two options enable a password to be set which must be entered before a complied show can be run and a feature to prevent screen snapshots being taken of the images in a show.

The final section "Run application or slideshow on exit" provides a feature to enable a subsequent application to run on completion of a show. This feature can be used to chain a number of shows together into a single continuous process.

From: https://docs.pteavstudio.com/ - **PTE AV Studio**

Permanent link: https://docs.pteavstudio.com/it-it/9.0/project-options/main?rev=1489388786



Last update: 2022/12/18 11:20