




Slide Duration and Full Slide Duration

Depending on the settings of Settings / Preferences and Project Options the duration seen in the Slide List can change.




If a single slide is added to the Slide List the Main Screen View looks like this:



The Status bar shows the Full (Slide) Duration and the (Slide) Duration. The Slide Icon displays the Slide Duration. For a single slide the Duration will equal the Full Duration because there is no following slide transition time to take into account - or the following slide transition time is zero.


The corresponding Objects and Animation Screen looks like this:




Adding another slide

Show Full Slide Duration Un-Ticked:

Adding a second slide with a 2 second transition time causes a change in the displayed (Slide) Duration. Note that the Full (Slide) Duration remains the same.




Objects and Animation View:




The (Slide) Duration of Slide 1 remains at 5 seconds but because Slide 1 is visible from the beginning of its own transition to the end of the Slide 2 transition (at varying opacities) its Full (Slide) Duration is 7 seconds.

Show Full Slide Duration Ticked:

Adding a second slide with a 2 second transition time causes a change in the Duration Icon on the Slide. Note that the Full (Slide) Duration and Full (Slide) Duration remain the same.



The Objects and Animation Screen remains the same.



Example

Key Frames in Slide 1 are placed at Zero and 7 seconds (7000ms)

Key Frames in Slide 2 are placed at 5 seconds (0ms) and 12 seconds (7000ms)

Below is a *Simulation* of two slides in Objects and Animation Screen:



The Timeline View:

The screenshot displays the PTE AV Studio software interface. At the top, the window title is "Project1 - PicturesToExe Deluxe". The menu bar includes "File", "Publish", "Project", "Slide", "Settings", and "Help". Below the menu bar are icons for file operations and a "Publish Show" button. The left sidebar shows a file explorer with folders like "Images", "Backgrounds", "DVD", "Fan01", "Fan02", "JIGSAW PIECES", "JPEGs", "2016_08_29", "Background...", "Backgrounds", "Help File Im...", and "loan". The main preview area shows a slide with a "HAPPY BIRTHDAY" image. Below the preview is a timeline with a scale from 0 to 0:13. Three slides are visible: "1. Untitled-7" (0:00-0:05), "2. Untitled-8" (0:05-0:10), and "3. Untitled-9" (0:10-0:13). Red arrows and text labels indicate durations: "Slide 1 Duration" (0:00-0:05), "Slide 1 Full Duration" (0:00-0:07), "Slide 2 Duration" (0:05-0:10), and "Slide 2 Full Duration" (0:05-0:13). The bottom status bar shows "Slide 1 of 3", "Full duration: 7.0 s", "Duration: 5.0 s", "1920 x 1080", "363 KB", and the file path "C:\Users\dave\Documents\Images\JPEGs\Backgrounds\Untitled-7.jpg".

From:
<https://docs.pteastudio.com/> - PTE AV Studio

Permanent link:
https://docs.pteastudio.com/en-us/9.0/how_to_v9/duration?rev=1491419259

Last update: 2022/12/18 11:20

